

## ↳ How to Install Extension

Once you placed the order you will receive link to download extension package in your email box.

You can also download extension package from your MyAccount > My Downloadable Products Section.

### Step 1

Extract downloaded extension package in your magento root folder using FTP(File Transfer Protocol) Tools. For verification of root folder you can see some folders inside magento root folder like app,bin,lib,phpserver and vendor etc.

### Step 2

Next Need to run some magento commands to install extension in your system , so connect with your server via SSH and go to magento root folder (e.g : cd /var/www/html/magento243) and run below commands one by one.

- php bin/magento setup:upgrade
- php bin/magento setup:static-content:deploy-f
- php bin/magento indexer:reindex
- php bin/magento cache:clean
- php bin/magento cache:flush
- chmod-R 777 var/ pub/ generated/

### Step 3

if your all commands run successfully than login to your system Admin Panel and goto Store > Configuration , if you will see new Tab in left side bar with MageCurious Logo it means extension installed successfully.

**Hey !! You Installed Extension Successfully Now it's time to Configure Extension.**

## About the Fingerprint Authentication Extension:

In Magento 2 admins can enable biometric web authentication for customer logins by using the Biometric WebAuthn Module. By navigating to Login Options within My Account settings, customers can initiate the WebAuthn registration process. The "**Register WebAuthn**" button facilitates a quick login process via the fingerprint scanner.

Subsequently, accessing the website becomes seamless for customers, requiring only a fingerprint scan on their smartphone. This module not only simplifies the login procedure but also eliminates the need for a password, offering a secure and user-friendly authentication experience.

## Key Features:

- Saves time and increases security for the personal data of customers
- Users do not require their password to sign in to the website
- Enable the customers to log in to the website using fingerprint scan
- Your smartphone's PIN can be used for both registering and logging in.

## Requirements:

1. **HTTPS:** WebAuthn requires a secure context, so your website must be served over HTTPS.
2. **Browser Support:** Ensure that the browsers you are targeting support WebAuthn. Most modern browsers, including Chrome, Firefox, Safari, and Edge, support WebAuthn.

## Note:

Using your fingerprint, you can log in to WebUthan on the same device you registered with.

If you want to use WebUthon in another phone, then register it there and then you can use it.

The webtuhn module is exclusively designed for Only mobile devices and functions accordingly.


## ↳ How to Configure Extension

### Step 1

To Configure Extension go to **Stores -> Settings -> Configuration -> Magecurious -> Fingure Print Auth**

### Step 2

**Fingure Print Auth Configuration:**




The screenshot shows the Magecurious Configuration page. At the top, there is a system message: "One or more indexers are invalid. Make sure your Magento cron job is running." Below this, the page title is "Configuration". On the left sidebar, the "STORES" menu item is highlighted. The main content area shows the "Fingure Print Auth" configuration section. Under the "GENERAL" tab, there is a setting "Allow Customer in Mobile Fingure Print to Authentication" with a dropdown menu currently set to "Disable". A callout box with an arrow points to the dropdown menu, containing the text "Enable or Disable Module".

**Enable Fingure print Auth:** Enable or Disable Module.

### Step 3


### Front End - Workflow

Navigate to the homepage.



Customers can log in by following the path shown in the image below.


Enter the log in **Email** and **Password** and press **Sign In**.




The screenshot shows a mobile browser interface for the Magecurious app. At the top, the status bar displays the time as 5:59 PM, a data speed of 176KB/s, and various connectivity icons. The browser address bar shows the URL 'magecurious.com/m2'. Below the browser, the app's header features a hamburger menu icon, the 'LUMA' logo, a search icon, and a shopping cart icon. The main content area is titled 'Customer Login' and 'Registered Customers'. It includes a sub-header 'If you have an account, sign in with your email address.' followed by two input fields: 'Email \*' and 'Password \*'. Below these fields are two blue buttons: 'Sign In' and 'Use Webauthn'. A link for 'Forgot Your Password?' is positioned below the buttons. A red asterisk note indicates '\* Required Fields'. The bottom section is titled 'New Customers' and contains text about the benefits of creating an account. The bottom of the screen shows the standard Android navigation bar.

## User Biometrics Registration

Now, after logging in the customer needs to go to the **Account section**.




Post which navigates to the **My Account > Login Options**.




## Registration WebAuthn :


Simply, click **Register WebAuthn**.




Further, the customer needs to **click** on the **more options** button.




For this purpose, the customer can **click this device** button to save his or her biometric data.




Here, the user will need to confirm his/her identity using biometrics to **verify fingerprints** or **Use Pin** as shown below.



Or Once you click **Use Pin**, a message will appear asking you to confirm your identity by entering your **lock screen PIN**.




Once, successful completion of the verification, the user's screen displays the biometric **WebAuth registration successfully** message.




## Cancel Webauthn :

After WebAuthn is **canceled**, fingerprints are **not available** for login.



## Use WebAuth to Log In

The customer can now **first add** their **email address**, and then click the '**Use WebAuthn**' button whenever he/she wants to log in. With a finger-print scan, you can verify as registered and login instantly.



5:59 PM | 176KB/s

magecurious.com/m2

LUMA

### Customer Login

#### Registered Customers

If you have an account, sign in with your email address.

**Email \***

**Password \***

**Sign In**

**Use Webauthn**


[Forgot Your Password?](#)

\* Required Fields

#### New Customers

Creating an account has many benefits: check out faster, keep more than one address, track orders and more.

After clicking the **Use WebAuthn** button, an image will appear below which allows you to enter your fingerprint





**Still Have any Doubt's ?**

**No Worries Just Contact Us Using Our Email / Phone**

Phone : +91 8980534268 , +91 8160580207

Email : support@magecurious.com

**Thank You !!!**